



Design Bulletin Glass Eye Users

Glass Eye Design Pointers

- ∅ Designs should be created to glass size as vector images
- ∅ Outline drawings are NOT acceptable.
- ∅ Fill desired areas with simulated DecoTherm colors. Unfilled areas are assumed to be clear glass.
- ∅ Include a color key naming the desired colors. Indicate which color is clear glass.

Acceptable Output Format from Glass Eye Software

The best way to export your artwork from Glass Eye is in a pdf format. To minimize the possibility of additional art charges, please output your Glass Eye artwork as follows:

1. Install CutePDF as discussed at www.dfly.com/help/faq4.html
2. Run Glass Eye 2000 and open your design.
3. Use the “Color Options” command and set your glass rendering to solid color
4. Press the “Show Hairlines” toolbar button to enable hairlines.
5. Use the Print command and choose “CutePDF Writer” as your printer.
6. Press the “Properties” button and choose a paper size large enough to hold your design on a single sheet.
7. Print your design; you’ll be asked for a filename, and also set a location (like your Desktop) where you’ll be able to find the result.
8. Send this PDF to your DecoTherm fabricator for production.
9. Contact the DecoTherm Design Studio if you have any questions 866.535.3439.

Please refer to complete DecoTherm Artwork Guidelines
www.DecoTherm.net